



Bookstore Manager

Technical Information Document

Windows 2000 Setup for Network Servers

Document Information:

Category	Hardware	O/S	Win2000	Last Modified	09/25/03
Author	JA				

Document Summary


Instructions for setting up Windows 2000 as a Network server for BSMGR.

Document Contents


NOTE: These instructions must be followed after installing the BSMGR RMS CD's. Please log in as the Administrator account.

Screen Size and Task Bar

- Right click on the desktop and click properties.



- Go to the Settings Tab and set the screen resolution to 800 X 600 and Colors to 16bit, click OK. Answer Yes to the question that comes up.




Bookstore Manager A head for your business. A heart for your ministry.


Bookstore Manager • 201 Fannin Street • Abilene, Texas • 79603 •
tel. 1-800-997-6724 • fax 1-325-673-0527 • www.bsmgr.com

Total Technology Solutions!

- Right click on the Task Bar and click Properties




- Ensure that the check box that says Auto Hide is unchecked and click OK




Creating USER Accounts

- Right click My Computer, then click Manage



- On the left hand side, click the plus sign next to Local Users and Groups
- Click the Users Folder
- In a blank area on the right hand side, Right click and choose New User...



- For User name, put RMS00
- For Full name, put RMS00
- For Description, put POS/Workstation
- Leave Password and Confirm Password blank
- Uncheck the box labeled, “User must change password at next logon”
- Check the box labeled, “User cannot change password”
- Check the box labeled, “Password never expires”
- Click the Create button
- Click the Close button

- You should now see the newly created RMS00 account listed.

- Double click on RMS00.
- Click the 2nd tab labeled, “Member Of”
- You should see the name Users listed under Member of:
- Click the Add... button

- You will now see a Select Groups window.
- Under Name, highlight Administrators and then click Add and you should see USER00\Administrators listed in the bottom box.

NOTE USER00 may not be the name listed depending on what your Computer Name is at this point. This is ok.

- Click OK

Name	In Folder
Administrators	USER00
Backup Operators	USER00
Guests	USER00
Power Users	USER00
Replicator	USER00
Users	USER00


- You should now see both Administrators and Users under Member of:

- Click OK

NOTE


You will need to do the above steps for adding RMS01-RMS09. You will also need to create a USER09 account.

- Once you are finished adding users, you can click the X in the top right window to close Computer Management.




Windows 2000 Environment Settings


- Right click on My Computer
- Click Properties




- Click the Advanced Tab
- Click the Environment Variables button



- Select PATH in the System Variables
- Click the Edit... button
- Go to the end of the Variable Value field and type:
;D:\ACU;D:\ETC
 Note: Replace D with the drive letter that RMS is installed on
- Click OK
- Click OK



- Click the Network Identification Tab
- Click the Network ID button



- At the, “Welcome to the Network Identification Wizard” Click Next.



- Click the radio button: This computer is a part of a business network, and I use it to connect to the other computers at work and then click Next.

Network Identification Wizard

Connecting to the Network
How do you use this computer?

Select the option that best describes your computer:

This computer is part of a business network, and I use it to connect to other computers at work.

This computer is for home use and is not part of a business network.

< Back Next > Cancel

- Click the radio button: My company uses a network without a domain and then click Next.

Network Identification Wizard

Connecting to the Network
What kind of network do you use?

Select the option that best describes your company network:

My company uses a network with a domain.

My company uses a network without a domain.

< Back Next > Cancel

- Change the Workgroup to BSMGR
- Note: If you choose to use a different workgroup name, ALL computers in your store network, including Quest units, must have the same workgroup name.
- Click Next

Network Identification Wizard

Workgroup
A workgroup is a group of computers that share files and resources.


Type the name of the workgroup to which this computer belongs. Windows uses this name in My Network Places to show you other computers in your workgroup.

If you do not know the name of your workgroup, go to the next screen.


Workgroup name:

< Back Next > Cancel


- At the Completing The Network Identification Wizard, click Finish




- If prompted to reboot, click the X in top right of the window so that it does not reboot




- On the Identification tab, click the Properties button.




- On the Computer Name Changes Window, change the Computer Name to USER00
 - 2 Zeroes, not o's
- Make sure the Workgroup is BSMGR
- Click OK



- When you click OK, you should get a dialog box that says, "Welcome to the BSMGR workgroup." Click OK. Click OK again and you will see the following message.




- When prompted to reboot, click Yes to reboot.




- After the computer reboots, log in as the RMS00 account

Network Settings

- Right click on My Network Places and click Properties
- Right click on Local Area Connection and click Properties



- Make sure the network components to the right are installed and checked.
- Note: The network adapter, labeled SMC EZ Card, will be replaced with the name of the network card that is installed in your server computer.



- Select TCP/IP and click Properties and fill in the required numbers.
- Enter an IP address for the server.

Note: Bookstore Manager recommends that you adhere to the following IP structure:

IP Address: 192.168.1.10

Subnet Mask: 255.255.255.0


Default Gateway: 192.168.1.1

Preferred DNS Server: 192.168.1.1

Alternate DNS Server should be Blank

NOTE 1: If you are installing Bookstore Manager on an existing network, please contact your network administrator for the proper IP configuration.

NOTE 2: If you don't have a router in your store, leave the "Default Gateway" and "Preferred DNS Server" lines blank



NOTE 3: If you have High Speed Internet, your DNS's may be different.


- Click OK

Sharing Network Drive and Printer

- Double click My Computer
- Right click on the drive that contains Bookstore Manager
- Click Sharing...




- Click New Share




Give it a Share Name of: C-Drive



- Set the User Limit to Maximum Allowed
- Click OK
- Click OK again
- Close the My Computer window



- Click Start
- Select Settings
- Click Printers




- Right click on the primary report printer (usually the one with the black checkmark)
- Click Sharing
- Click the dot next to Shared-As
- Give it a name of @printer
- Click OK
- Click the "X" in the top right of the window to close the "Printers" window.




Setting up Shortcuts


- Right click on the Start button
- Click Open All Users
- Double click Programs
- Double click Startup




- Click on File, then New, then Shortcut



- Type: D:\ACU\WRUN32.EXE MENU 00
(where D is the drive letter of RMS)
 - The first number after “MENU” is the “USER_NUM”, the second number is the “REG_NUM”. If the server is also a point of sale, use 11 in place of 00 for point of sale #1.
- Click Next




- Type: Bookstore Manager where it asks for a name
- Click Finish



- Right click on the newly created shortcut
- Click Properties

- Set the Start in to **D:\BOOK**
(where D is the drive Bookstore Manager is installed on)
- Click Change Icon
- Type D:\ACU\BSMGR.ICO
(where D is the drive Bookstore Manager is installed on)
- Click OK
- Click OK again



- Right click the newly created icon and click Send To, then click Desktop (create shortcut)
- Click the “X” in the top right of the window to close the “Startup” folder.
- When you go into BSMGR, you will get a dialog box that shows up the first time you run BSMGR indicating “Fast Mode” Click OK then click the BSMGR icon again to Start BSMGR. You will get a message that you need to run REGOCX
- To run REGOCX in Bookstore Manager, click Utilities and down to Operating System. Then at the DOS prompt, type: REGOCX <Enter> You will see several screens that should say, “DllRegisterServer in succeeded.” Click OK on these.

